Firmware and Android App Update for

AAT Mini, AAT, AAT Max, MW, or MW MAX

AAT/MW Firmware and Android App Download Procedure

- Connect to the internet, not the AAT/MW tool, and download the latest appropriate update zip file from www.sunsight.com/support. This zip file will contain all files required for the update. There may be files for the AAT/MW update, the Android app update, as well as other documentation.
- 2) Unzip the downloaded file(s) to a known location. Files that end in .bin are for the AAT/MW tool, files that end in .apk are for the Sunsight Android app

Sunsight Android App Update Procedure (perform before updating AAT/MW)

- 1) Delete the current app from the Android Device
- 2) Navigate to the location where the .apk file was saved when it was unzipped in step 2) above
- 3) Double click on the .apk file to install the new app. Follow on-screen instructions

AAT/MW Firmware Update Procedure

- ALL REPORTS MUST BE DOWNOADED PRIOR TO UPDATING THE AAT/MW FIRMWARE
- FIRMWARE UPDATE IS PERFORMED OVER WIFI. FIRMWARE CANNOT BE UPDATED USING THE USB-C CABLE CONNECTION
- THE AAT/MW MUST HAVE ENOUGH BATTERY LEVEL TO PERFORM THE UPDATE, IT IS PREFERRED TO CONNECT THE CHARGER DURING THE UPDATE
- DO NOT POWER OFF THE AAT/MW DURING THE FIRMWARE UPDATE PROCEDURE! TO DO SO COULD REQUIRE RETURNING THE UNIT TO SUNSIGHT FOR REPAIR.
- TILT AND ROLL CALIBRATION MUST BE PERFORMED AFTER THE FIRMWARE UPDATE IS COMPLETE USING THE AAT/MW'S ONBOARD TILT AND ROLL CALIBRATION. THIS PROCEDURE TAKES ABOUT 1 MINUTE.

The update process takes about 10 minutes to complete. Make sure to let the entire update process complete.

- 1) Connect to the AAT/MW's WiFi network in your usual manner and navigate to the Firmware Update page (Home->Tools->Firmware Update)
- 2) Record the version of firmware displayed at the bottom of the page
- 3) Select "Choose File", then browse and select the downloaded .bin file
- 4) Select "Update". During the firmware update process the AAT/MW will restart and the WiFi connection will be lost.
- 5) Wait for the blue LED to go solid on the AAT/MW keypad and then reconnect to the AAT/MW. This will take about 3 minutes.
- 6) Once the update is complete, confirm the firmware version displayed at the bottom of the Firmware Update page is higher than the one recorded in step 2) above.

Firmware and Android App Update for

AAT Mini, AAT, AAT Max, MW, or MW MAX

7) Perform the tilt and roll calibration using the Tilt and Roll Calibration feature. Navigate to Home Page-> Tools -> Tilt Roll Calibration. Follow the instructions. This will take about 1 minute.